DATlib

Made in France.

Deal with it.

Table of contents

| About DATlib | 5 |
|---|----|
| Concepts and preliminary notices | 5 |
| nstallation | 6 |
| Features | 7 |
| Input management | 7 |
| Program loop | 7 |
| Provided graphics types | 8 |
| Vblank handlers | 9 |
| DAT_vblank | 9 |
| DAT_vblankTI | 9 |
| Timer interrupt | 10 |
| Job meter | 11 |
| Debug dips | 11 |
| Sprite Pools | 12 |
| Vblank callbacks | 13 |
| Color streams | 13 |
| Tools | 14 |
| Buildchar (character ROM) | 14 |
| Buildchar (fix ROM) | 18 |
| Charsplit | 20 |
| Framer | 21 |
| Animator | 22 |
| Library reference | 24 |
| Command buffers formats | 24 |
| Library defines | 25 |
| Flip modes defines | 25 |
| Job meter defines | 25 |
| Input related defines | 26 |
| Library variables | 28 |
| General purpose components | 29 |
| MEMBYTE, MEMWORD, MEMDWORD | 29 |
| volMEMBYTE, volMEMWORD, volMEMDWORD | 30 |
| VRAM_SPR_ADDR, VRAM_FIX_ADDR, VRAM_SHRINK_ADDR, VRAM_SHRINK, VRAM_POSY_ADDR, VRAM_POSY, VRAM_POSX_ADDR, VRAM_POSX | 31 |

| | fixJobPut | . 32 |
|---|---|------|
| | palJobPut | . 33 |
| | SC1Put | . 34 |
| | SC234Put | . 35 |
| | clearFixLayer, clearFixLayer2, clearFixLayer3 | 36 |
| | clearSprites | . 37 |
| | disableIRQ | . 38 |
| | enableIRQ | . 39 |
| | initGfx | 40 |
| | jobMeterColor | 41 |
| | jobMeterSetup, jobMeterSetup2 | 42 |
| | loadTlirq | 43 |
| | SCClose | . 44 |
| | setup4P | 45 |
| | unloadTlirq | 46 |
| | waitVBlank | 47 |
| S | ring / Text components | . 48 |
| | About string formats | . 48 |
| | sprintf2 | . 48 |
| | sprintf3 | 49 |
| | fixPrint, fixPrint2, fixPrint3, fixPrint4 | . 50 |
| | fixPrintf, fixPrintf1, fixPrintf2, fixPrintf3 | . 51 |
| Р | ctures components | . 52 |
| | picture | . 52 |
| | pictureInfo | . 53 |
| | pictureHide | . 54 |
| | pictureInit | . 55 |
| | pictureMove | . 56 |
| | pictureSetFlip | . 57 |
| | pictureSetPos | . 58 |
| | pictureShow | . 59 |
| S | crollers components | 60 |
| | scroller | 60 |
| | scrollerInfo | 61 |
| | scrollerInit | 62 |
| | scrollerSetPos | 63 |

| Animated sprites components | 64 |
|---|-----|
| aSprite | 64 |
| spriteInfo, animStep, sprFrame | 66 |
| aSpriteAnimate | 67 |
| aSpriteHide | 68 |
| aSpriteInit | 69 |
| aSpriteMove | 70 |
| aSpriteSetAnim, aSpriteSetAnim2 | 71 |
| aSpriteSetStep, aSpriteSetStep2 | 72 |
| aSpriteSetAnimStep, aSpriteSetAnimStep2 | 73 |
| aSpriteSetFlip | 74 |
| aSpriteSetPos | 75 |
| aSpriteShowaSpriteShow | 76 |
| Sprite Pools components | 77 |
| spritePool | 77 |
| spritePoolClose | 78 |
| spritePoolDrawList, spritePoolDrawList2 | 79 |
| spritePoolInit | 80 |
| Color steam components | 81 |
| colorStream | 81 |
| colorStreamInfo, colorStreamJob | 82 |
| colorStreamInit | 83 |
| colorStreamSetDos | 8/1 |

About DATlib

DATlib is a library designed for the NeoBitz/NeoDev environment. It is designed to replace libvideo and libinput from the original kit.

Its goal is to provide easy functionality trough base elements (scroller, picture and animated sprite) which you are prone to use in your software, and allow better performance than basic libraries while writing less code.

Tools are also improved over standard ones to allow more colors (no longer limited to one palette per object), auto animation support, smaller data...

Combined tools and library allow easier coding while providing better performance and easy syncing between vblank and sprites update, greatly reducing tearing issues.

Concepts and preliminary notices

First of all, there is a quick demo program provided in the archive with source code, which you can explore and play along with to get familiar with the library and tools, or use as a stepping stone for your project.

DATlib will occupy about 10KB of the system ram.

The main outline of how this library works is that graphic updates are queued into buffers (also called draw lists / command buffers) that are processed during vblank. There is currently four command buffers: tiledata commands buffer (SC1 buffer, VRAM 0x0000 – 0x6FFF operations), sprites control commands buffer (SC234 buffer, VRAM 0x8000- 0x85FF operations), palette jobs commands buffer (PALJOBS buffer, palette ram operations) and fix jobs command buffer (FIXJOBS buffer, fix layer operations). This means you can -for example- update a sprite position anywhere in your code, it will automatically be synced with and updated during next vblank.

Many components of this library evolve around the concept of base sprite and base palette:

Base sprite designates the starting sprite to use for said element. As an example a 4 tiles width picture with base sprite set to 10 will therefore use sprites #10 #11 #12 #13 to display.

Base palette is basically the same concept as base sprite, applied to color palettes.

It is currently up to the user to manage sprites and palettes to make sure no overlaps occurs across different elements.

Installation

Requirements: main NeoBitz dev package is required, make sure it is correctly installed and set up.

To install required files, merge the content of the archive's "NeoDev" folder with your current NeoDev installation.

DATlib is designed to supersede libvideo and libinput, make sure your remove those from your linker options in your project makefile and add DATlib library (remove -lvideo and -linput, add -lDATlib).

IE:

becomes

Add <input.h> and <DATlib.h> in your program includes.

If you use BuildChar to convert your data into tilemaps (most likely you will), also add the .h files made by it to your project.

Use the provided common_crt0_cart.s and crt0_cart.s file for your project, replacing older ones. (common_crt0_cd.s and crt0_cd.s for CD projects).

Features

Input management

As standard libinput is dropped when installing DATlib, input defines are provided in the new input.h include file. Input values can be read with the volMEMBYTE() macro from the BIOS memory region.

Support is provided for mahjong controllers as well as 4P adapters, check library reference section for available defines.

Example:

Program loop

Using the library requires using a defined program flow for everything to work together.

While there are many ways to arrange code and use functionalities, here is a sample, basic program loop:

Provided graphics types

DATlib provides three base graphical elements that should fulfill most needs:

picture

- simple picture type
- allows display, positioning and flipping of static pictures
- when setting picture position, you are setting top left pixel position
- uses picture tile width sprites (ie: 64px width picture = 4 tiles width = 4 used sprites)

scroller

- type used to display a scrolling plane
- 8 way scrolling ability
- no map size limit
- uses 21 sprites, regardless of plane dimensions

animatedSprite

- provides support for animated sprites
- allow display, positioning, flipping and animating sprites
- animation system supports repeats and animation linking
- up to 65536 animations, unlimited animation steps
- Allocated mode / Sprite pool mode
- used sprites depends on currently displayed frame. If using allocated mode, good practice
 is to plan enough sprites to fit the widest frame

<u>Note:</u> Animated sprites uses a different way to position themselves. Each frame location is relative to a fixed reference point. This is due to the nature of animations, often using a set of frames of different sizes and alignments (to avoid encasing a few pixels in a large picture frame, saving space and CPU time). Positioning operations on animated sprites refer to positioning the reference point. Flipping animated sprites is done around the reference point. It is possible to revert back to a more classic cpprdinates system by using the strict coordinates flag.

Vblank handlers

Vblank handlers are interrupt handlers provided by the library, required for proper operation. Those have to be set up as your vertical interrupt (IRQ2) vector.

DAT_vblank

Standard vblank handler.

Operation:

- sets job meter to red
- process tiledata buffer
- process sprites control buffer
- process palette jobs buffer
- process fix jobs buffer
- sets job meter to orange
- resets draw lists, updates frame counter
- checks and process debug dips
- acknowledges IRQ, kicks watchdog, calls SYSTEM IO (BIOS)
- sets job meter to green
- returns

Note: Job meter colors are only updated under select circumstances, see debug dips section.

DAT_vblankTl

Vblank handler with timer interrupt support.

Operation:

- Load base and reload timing values (if timer interrupt enabled)
- Branch to DAT vblank for standard operations

<u>Notes:</u> When using timer interrupts, requested LSPC mode must be written to the LSPCmode variable (ushort). This is due to the LSPC mode hardware register being manipulated to set timer values, therefore needing a reference value of requested settings to preserve them. If using standard vblank handler, the LSPCmode variable will be ignored and therefore you must write directly to the register when needed.

When using timer interrupts, user must use IRQ safe versions of functions when available. Thoses are slightly slower than the regular ones but are required to avoid VRAM corruption by interrupts.

Timer interrupt

Base functionality is provided for timer interrupts, allowing to change one or two VRAM value on every (or select set of) scanline.

To enable timer interrupt functionalities:

- set DAT vblankTI as your vblank IRQ vector
- set DAT TIfunc as your timer IRQ vector

<u>Notes:</u> make sure you set variable TinextTable (uint) to 0 before enabling IRQ when using timer interrupt. This is done in the default init code, but make sure to keep it if customizing files. Timer interrupt related code uses the USP register, make sure you code doesn't conflict.

Using timer interrupt:

To work with timer interrupt you need to prepare data in a WORD table, storing VRAM address and data combos.

Format for the data table is:

- VRAM address n (1 ushort)
- VRAM data n (1 ushort)
- VRAM address n+1 (1 ushort)
- VRAM data n+1 (1 ushort)
- (etc...)
- end marker (2 ushort, 0x0000 0x0000)

For correct behavior it is required to use two alternating tables. One table for currently displaying frame, another one to prepare data for next frame.

Timer IRQ function must be set up with loadTIirq() prior to use.

Timer IRQ is available for single and dual data writes for each triggering. See loadTiirq() section.

Startup timer interrupt:

- set base and reload timers
- put pointer to data table for next frame in the TinextTable variable

Stop timer interrupt:

set TInextTable to null (0)

<u>Notes:</u> When data last value is processed, the timer interrupt will be disabled for the rest of the frame until next vblank. This avoids triggering unnecessary IRQ, as they are CPU consuming. Default timer values are provided for first raster line triggering and each line repeat: TI_ZERO and TI_RELOAD. Timer interrupt will be disabled if TinextTable is null. Timer interrupt will be disabled if first table entry is end marker.

Job meter

Base job meter support is provided by the library.

Job meter allows basic profiling of your code, by having a visual representation of how much CPU time is used. Using different colors lets you observe CPU usage of every procedure, allowing targeting of things to optimize.



Job meter example:

Green color: free CPU time
Blue color: animation procedures
Red color: vblank sprites updates
Orange color: post vblank SYSTEM IO

<u>Note:</u> Setting job meter colors during active display will issue a pixel of said color on screen (on real hardware). This is an issue with the hardware that can't be avoided, therefore make sure to use job meter in debug builds only.

Debug dips

Some of DATlib features are enabled through debug dips. Enable dev mode into bios then set the requested dips to 1.

- Debug dip 2-1
 Enable vblank job meter color updates.

 Vblank interrupt will color draw buffers processing as red job, and post jobs like SYSTEM_IO in orange.
- Debug dip 2-2
 Displays current raster line # when draw buffers are done being processed.
- Debug dip 2-3
 Displays a rough usage meter for SC1 and SC234, FIXJOBS and PALJOBS buffers
- Debug dip 2-4 ~2-8
 Unused / reserved future use.

Sprite Pools

Sprite pools are an alternate way to handle sprites rendering. It consists of a reserved sprites batch which is then used to display assets.

This technique is reminescent of double buffering, but using sprites.

It differs from the previous basic, "allocated" draw mode by many ways:

- Sprite tilemap/position data is written during active frame, alleviating vblank load
- Sprite tilemap/position data is fully rewritten every frame
- Removes the need to manage baseSprite from **aSprite** handles, they are drawn in the order they are submitted
- Submit order drawing allows for easier sprites sorting/priority change
- No baseSprite management means less sprite loss, when current frame is smaller than the maximum reserved space

Base operation sketch


A spritePool entity must be initialized providing a pool size (# of sprites) and a starting position for this pool (baseSprite). Pool size should be aimed at twice the size of an average scene. If an average frame requires 80 sprites, ideally allocate 160.

To draw into the sprite pool, user must submit an array of pointers to **aSprite** handles, followed by a null pointer end marker.

Drawing in the sprite pool alternates way every frame (WAY_UP/WAY_DOWN). When going UP, pool uses sprites from pool start toward pool end, when going DOWN, from pool end toward pool start. User must supply the top or bottom end of the pointer array, to fit needs.

Tilemap and X position data is written into vram during active display, Y position is updated during vblank.

In case of heavy load, it is possible the sprite needs overlaps with the currently used sprites from previous frame. In this case overlapping sprite needs are queued for update during next vblank:



This provides a failsafe and user transparent operation in most scenarios, however exceeding the total pool side will lead to unexpected results and adjacent sprites corruption.

Note: As **s**prite pools are designed to update VRAM during active frame, this feature isn't interrupt safe (using it alongside timer innterrupt can corrup VRAM info).

Vblank callbacks

Vblank callback function are available by using the supplied pointers:

- VBL callBack: callback pointer to function to be called after a regular Vblank
- VBL skipCallBack: callback pointer to function to be called after a skipped frame Vblank

Callback functions are called at the very end of the Vblank interrupt procedure and after SYSTEM_IO occurred.

As all registers (except for A7) are restored when the callback function returns, user can trash them without caring about saving them.

Color streams

When creating a large background plane, an issue can arise with color palettes being too numerous to fit withing the available ressources.

Color streams are provided as a solution, allowing the streaming color data into palette RAM as scrolling advances.

When requesting a color stream from buildchar, orientation must be specified (horizontal/verttical) to indicate scan orientation. Scanning along the largest axis will usually provide the best results. IE a "landscape" orientation scroller should be using horizontal parameter.

When initializing a color stream, user can choose to load the start or end configuration, matching palettes state at start or end of scroller. It is advised to initialize streams with the configuration matching the scroller position the closest.

Once initialized user can request streams to advance to select position, required palette jobs will be buffered and processed on next Vblank.

Note: Be wary of large jumps in scrollers when using color streams, as it could induce a lot of palettes shuffling and possibly overflows the available palette jobs buffer.

Tools

Buildchar (character ROM)

Command line tool used to convert your graphics elements into tiles, tilemaps and palettes.

Input

- chardata.xml

</chardata>

Contains description of assets to include into tile data.

```
Example chardata.xml file:
<?xml version="1.0" encoding="UTF-8" ?>
<chardata>
   <setup>
          <starting_tile fillmode="dummy">256</starting_tile>
   </setup>
   <scrl id="ffbg_b">
          <file>gfx\ffbg_b0.png</file>
          <auto1>gfx\ffbg_b1.png</auto1>
          <auto2>gfx\ffbg_b2.png</auto2>
          <auto3>gfx\ffbg_b3.png</auto3>
   </scrl>
   <pict id="ffbg_c">
          <file>gfx\ffbg_c.png</file>
          <flips>xyz</flips>
   </pict>
   <sprt id="bmary_spr">
          <file>gfx\bmary.png</file>
          <flips>xyz</flips>
          <frame>0,0:4,7</frame>
          <frame>4,0:4,7</frame>
          <frame>8,0:4,7</frame>
          <frame>12,0:4,7</frame>
          <frame>16,0:4,7</frame>
          <frame>20,0:4,7</frame>
          <frame>24,0:4,7</frame>
          <frame>28,0:4,7</frame>
          <frame>32,0:4,7</frame>
          <frame>36,0:4,7</frame>
          <frame>40,0:4,7</frame>
          <frame>44,0:4,7</frame>
   </sprt>
```

Nodes details:

o <setup>

Contains general settings:

<starting_tile>

Defines starting tile # (decimal). Used to leave blank tiles at the beginning of the char.bin file, useful if you need room to fit things like a character font at the beginning of the tileset. Additional parameter fillmode (none/dummy) defines if skipped tiles are to be filled or not.

<charfile>

Defines output character file name. Optional, defaults to "char.bin".

<mapfile>

Defines output tilemaps data file name. Optional, defaults to "maps.s".

<palfile>

Defines output palettes data file name. Optional, defaults to "palettes.s". It's possible to use same name as mapfile, to merge data in the same file.

<incfile>

Defines output include file name. Optional, defaults to "externs.h".

o <import>

Used to import binary data. Will copy the raw binary data into the output file. File size must be multiples of 128 bytes (single tile size).

<file>

Binary file to import.

o <scrl>

Used to declare a scroller

id (attribute)

Literal name the scroller will be referenced by in C code.

colorStream (attribute)

Set this attribute to "horizontal" or "vertical" value to generate **colorStream** data for this scroller.

<file>

PNG file of the display area.

<auto1> to <auto7>

Additional pictures when using auto animation features.

o <pict>

Used to declare a picture

id (attribute)

Literal name the picture will be referenced by in C code.

<file>

PNG file of the picture.

<flips>

Flip modes wanted for this picture (optional).

X = horizontal flip

Y = vertical flip

Z = horizontal & vertical flip

o <sprt>

Used to define an animated sprite

id (attribute)

Literal name the animated sprite will be referenced by in C code.

<file>

PNG file containing all animation frames.

<flips>

Flip modes wanted for this animated sprite (optional).

X = horizontal flip

Y = vertical flip

Z = horizontal & vertical flip

<frame>

Defines a frame, format is: top,left coordinate:width,height Unit is tile (16px)

See Framer tool section to easily set up frames

About input files format:

Picture files used in chardata.xml must be PNG format, 32bppArgb. Define transparency by pink color (#ff00ff), or simply use transparency. Size must be multiples of 16.

About colors:

There is no limits color wise, as long as each tile is transparency + 15 colors max, you can use pics with hundreds of colors.

If your file is rejected for using too many colors per tile, erroneous tiles will be shown in a reject.png file.

About ID:

Each declared entity will generate an extern C object named <id>, as well as a palettes object named <id>_Palettes.

Output

- char.bin

Your tile data, linear binary output.

Convert to cart or CD format if needed by using the CharSplit tool.

- maps.s

Tilemaps data, add to makefile to compile and link into your project.

palettes.s

Palettes data, add to makefile to compile and link into your project.

externs.h

Extern definitions of your data. Include into your C program to use data.

Mixing auto4 and auto8 tiles

It is possible to mix up auto4 and auto8 tiles on the same file when using auto animation. To do so, use the supplied auto4 marker tile (auto4_tile.png) on your <auto4> file to designate an auto4 tile.

Tile distribution across mixed up files is as follow:

| | <file></file> | <auto1></auto1> | <auto2></auto2> | <auto3></auto3> | <auto4></auto4> | <auto5></auto5> | <auto6></auto6> | <auto7></auto7> |
|-------|---------------|-----------------|-----------------|-----------------|-----------------|-----------------|-----------------|-----------------|
| Auto4 | Tile #0 | Tile #1 | Tile #2 | Tile #3 | End marker | 1 | gnored data | a |
| Auto8 | Tile #0 | Tile #1 | Tile #2 | Tile #3 | Tile #4 | Tile #5 | Tile #6 | Tile #7 |

Buildchar (fix ROM)

Buildchar can also be used to generate FIX ROM character data.

Use the fileType="fix" tag inside the setup node to specify a FIX ROM file.

Fix data is split into 16 "banks" of 256 characters.

Input pictures must be sets of 256 characters forming a 128px*128px area bank.

Picture can contain multiple character sets, however layout must remain 128px height and 128px multiples width.

You can load multiple pictures in the same bank. As they will be merged together, make sure data doesn't overlap.

Please note buildchar doesn't optimize character data, as characters location is very often a programmer's choice (fonts needing to be at set position, specific health bar setup, etc...). In the same manner, there is no tilemap data output. You have to write the data fitting your needs (see 16bit strings format and fixJobPut).

Input

fixdata.xml

Contains description of assets to include into fix data.

Example fixdatadata.xml file:

Nodes details:

o <setup>

Contains general settings:

<charfile>

Defines output character file name. Optional, defaults to "char.bin".

<palfile>

Defines output palettes data file name. Optional, defaults to "palettes.s". It's possible to use same name as mapfile, to merge data in the same file.

<incfile>

Defines output include file name. Optional, defaults to "externs.h".

o <import>

Used to import binary data. Will copy the raw binary data into the output file.

This can be used to import a standard system font.

File size must be multiples of 32 bytes (single character size).

Bank (attribute)

Destination bank #.

<file>

Binary file to import.

o <fix>

Import a characters set

Bank (attribute)

Destination bank #.

id (attribute)

Literal name for the palette data that will be referenced by in C code.

<file>

PNG file of the characters data.

Charsplit

Command line tool used to convert raw character data issued by buildchar to either cart or CD format files.

<u>Usage:</u>

Example:

```
charsplit char.bin -cart game
will split char.bin into game.c1 and game.c2 files for cart system use.
```

Framer

Tool used to delimit animated sprites frames.

Each animated sprite must be assigned a set of frames before being processed by the buildchar tool.


<u>Input</u>

chardata.xml
 Click the open button and select the xml file containing reference to your animated sprites assets.

<u>Output</u>

- chardata.xml
Click the save button to update xml file with the new/updated frames.

Usage:



Framer is very straightforward to use. Open your xml file, then select the animated sprite you want to work with from the drop down menu.

If the xml file already contains data, existing frames will be listed to be updated/removed.

To add a new frame, simply select it by clicking and dragging mouse, then click the add button, or press the space bar.

When done, click save to update the xml file, which is then ready to use with buildchar for processing.

Animator

Tool used to animate animated sprites.

Each animated sprite you process with the buildchar tool must be assigned at least one animation with the animator tool for proper compilation and linking of your project.

<u>Input</u>

When defining an animated sprite, buildchar will output a subfolder containing frames cutouts. Open this folder in Animator.


animdata.xml
 This is your save file regarding this animation. If found inside folder, animator will load it.

Output

- animdata.xml
 This is your save file regarding this animation. Hit save button to save your work.
- <id>_anims.s
 Animations file, this should already be an include in your maps.s file by buildchar tool.
- <id>.h
 Contains animations C defines, should already be included in your externs.h file by buildchar tool.

Using Animator:

Main window is divided into 3 areas



1 Preview area

This area allows you to visually align frames and preview animations. Change scale for better viewing. Reference point is visualized by the intersection of the two red axes. When setting position of animated sprites in your code, you are setting the position of this reference point.

2 Sprite and frames data area

This area will list and provide a quick preview of all the frames you created using the framer and buildchar tools, making sure you exported them correctly.

3 Animations area

This is the main section to edit and check animations

Adding an animation: Input animation name in text field and press the [Add] button, the new animation will appear in the animations list.

Edition an animation: Select the animation you want to edit in the animations list. Input repeat count and link data for selected animation. Repeats are the number of times the animation will be repeated after initial play. Link allows you to branch to another animation once current animation is done displaying (including repeats). You can link an animation to itself to create a loop. If no link is selected the last animation frame will remain of screen after animation is done.

From there on, double click on frames in frames list to add animation steps.

You will have to input frame position for each step (X & Y field, or arrow buttons) as well as step timing (T field). Timing is the number of display frames the selected step remains on screen. Mod all steps checkbox will allow you to edit all steps at the same time.

You can adjust steps order or delete steps by using buttons under the steps list.

Animations IDs

Each animation created with the animator tool will generate a C define that can therefore be used when setting animations.

Format is <id>_ANIM_<animation name> (all uppercase).

As an example, building animations named WALK and IDLE for animated sprite defined with ID "mycharacter" will generate MYCHARACTER_ANIM_WALK and MYCHARACTER_ANIM_IDLE defines.

Exporting data

Use the [Export] button in the toolbar to export animation data into your project for compilation/linking.

Keyboard shortcuts

Shift + arrow keys: move frame of currently selected step

Space bar: start/stop current animation playback

Library reference

Command buffers formats

SC1 buffer

Each SC1 buffer entry is two 32bit uint:

| 31-24 | 23-18 | 17-16 | 15-0 |
|-------------|------------|-------|--------------|
| Palette mod | Tile count | 00 | VRAM address |

| 31-0 |
|-------------------|
| Tile data address |

Buffer has a 0x00000000 end marker.

SC234 buffer

Each SC234 buffer entry is two 16bit ushort:

| 15-0 | |
|--------------|--|
| VRAM address | |

| 15-0 |
|-----------|
| VRAM data |

Buffer has no end marker (size is computed from SC234ptr value).

PALJOBS buffer

Each PALJOBS buffer entry is two 32bit uint:

| 31-16 | 15-5 | 4-0 |
|------------------|----------------|-------|
| Palettes count-1 | Palette number | 00000 |

| 31-0 | |
|----------------------|--|
| Palette data address | |

Buffer has a 0xffffffff end marker.

FIXJOBS buffer

Each FIXJOBS buffer entry is two 32bits uint:

| 31-16 | 15-12 | 11-8 | 7-0 |
|--------------|-----------|------|-------------|
| VRAM address | Palette # | 0000 | VRAM modulo |

| 31-0 |
|------------------|
| FIX data address |

Buffer has a 0x00000000 end marker.

Library defines

Flip modes definesFlip modes used for graphical elements to define orientation.

| FI | lin | modes |
|----|-----|---------|
| | שוו | IIIOucs |

| unflipped |
|------------------------------|
| horizontal flip |
| vertical flip |
| horizontal and vertical flip |
| horizontal and vertical flip |
| |

Job meter defines

Basic colors used for job meter

| \sim | ۱۸ | ro |
|--------|----|----|
| C | o | 15 |

| Colors | | |
|-----------------|-----------------|--|
| JOB_BLACK | | |
| JOB_WHITE | | |
| JOB_LIGHTRED | JOB_LIGHTGREEN | |
| JOB_RED | JOB_GREEN | |
| JOB_DARKRED | JOB_DARKGREEN | |
| JOB_LIGHTBLUE | JOB_LIGHTPURPLE | |
| JOB_BLUE | JOB_PURPLE | |
| JOB_DARKBLUE | JOB_DARKPURPLE | |
| JOB_LIGHTCYAN | JOB_LIGHTYELLOW | |
| JOB_CYAN | JOB_YELLOW | |
| JOB_DARKCYAN | JOB_DARKYELLOW | |
| JOB_LIGHTORANGE | JOB_LIGHTPINK | |
| JOB_ORANGE | JOB_PINK | |
| JOB_DARKORANGE | JOB_DARKPINK | |
| JOB_LIGHTGREY | | |
| JOB_GREY | | |
| JOB_DARKGREY | | |
| | | |

Input related definesDefines used to read controller data and check button presses. All data registers are byte size.

Hardware registers

| P1_HW | hardware controller port 1 (negative logic) |
|-------|---|
| P2_HW | hardware controller port 2 (negative logic) |

Bios registers

| Dios registers | |
|----------------|-------------------------------|
| P1_STATUS | player 1 status |
| P1_PAST | player 1 previous frame data |
| P1_CURRENT | player 1 current data |
| P1_EDGE | player 1 active edge data |
| P1_REPEAT | player 1 repeat data |
| P1_TIMER | player 1 repeat timer |
| | |
| P2_STATUS | player 2 status |
| P2_PAST | player 2 previous frame data |
| P2_CURRENT | player 2 current data |
| P2_EDGE | player 2 active edge data |
| P2_REPEAT | player 2 repeat data |
| P2_TIMER | player 2 repeat timer |
| | |
| P1B_STATUS | player 3 status |
| P1B_PAST | player 3 previous frame data |
| P1B_CURRENT | player 3 current data |
| P1B_EDGE | player 3 active edge data |
| P1B_REPEAT | player 3 repeat data |
| P1B_TIMER | player 3 repeat timer |
| | |
| P2B_STATUS | player 4 status |
| P2B_PAST | player 4 previous frame data |
| P2B_CURRENT | player 4 current data |
| P2B_EDGE | player 4 active edge data |
| P2B_REPEAT | player 4 repeat data |
| P2B_TIMER | player 4 repeat timer |
| DC CURRENT | |
| PS_CURRENT | current select/start data |
| PS_EDGE | active edge select/start data |
| | |

Controller types (status byte value)

| | - |
|-----------------------------------|-------------------------------|
| CTRL NOCONNECT | not connected |
| _ | |
| CTRL STANDARD | standard controller |
| | |
| CTRL EXPANDED | expanded controller (4P mode) |
| · · · · · · · · · · · · · · · · · | |
| CTRL KEYBOARD | keyboard |
| CTITE_RETBOARD | • |
| CTRL MAHJONG | mahjong controller |
| CTIVE_TIMITS ONG | manjong controller |

Controller positions

| JOY_UP | lever up |
|------------|--|
| JOY_DOWN | lever down |
| JOY_LEFT | lever left |
| JOY_RIGHT | lever right |
| JOY_A | A button |
| JOY_B | B button |
| JOY_C | C button |
| JOY_D | D button |
| | |
| P1_START | player 1 start button (select/start register) |
| P1_SELECT | player 1 select button (select/start register) |
| P2_START | player 2 start button (select/start register) |
| P2_SELECT | player 2 select button (select/start register) |
| P1B_START | player 3 start button (select/start register) |
| P1B_SELECT | player 3 select button (select/start register) |
| P2B_START | player 4 start button (select/start register) |
| P2B_SELECT | player 4 select button (select/start register) |
| | |

Mahjong controller related

| Manjorig controller related | | | |
|-----------------------------|---------------------------------------|--|--|
| P1_JONG_A_G | player 1 mahjong data, A-G buttons | | |
| P1_JONG_H_N | player 1 mahjong data, H-N buttons | | |
| P1_JONG_BTN | player 1 mahjong data, action buttons | | |
| | | | |
| P2_JONG_A_G | player 2 mahjong data, A-G buttons | | |
| P2_JONG_H_N | player 2 mahjong data, H-N buttons | | |
| P2_JONG_BTN | player 2 mahjong data, action buttons | | |
| | | | |
| JONG_A | A button | | |
| JONG_B | B button | | |
| JONG_C | C button | | |
| JONG_D | D button | | |
| JONG_E | E button | | |
| JONG_F | F button | | |
| JONG_G | G button | | |
| JONG_H | H button | | |
| JONG_I | I button | | |
| JONG_J | J button | | |
| JONG_K | K button | | |
| JONG_L | L button | | |
| JONG_M | M button | | |
| JONG_N | N button | | |
| JONG_PON | PON button | | |
| JONG_CHI | CHI button | | |
| JONG_KAN | KAN button | | |
| JONG_RON | RON button | | |
| JONG_REACH | REACH button | | |
| | | | |

Library variables

General variables

| uint | DAT_frameCounter | frame counter |
|--------|-----------------------|--------------------------------------|
| uint | DAT_droppedFrames | dropped (skipped) frames counter |
| uint | *VBL_callBack | VBlank callback function pointer |
| uint | *VBL_skipCallBack | VBlank callback function pointer |
| | | (skipped frame) |
| uint | SC1[760] | draw list for tilemap data |
| uint | *SC1ptr | pointer to tilemaps data draw list |
| ushort | SC234[2280] | draw list for sprite control |
| ushort | *SC234ptr | pointer to sprites control draw list |
| uint | PALJOBS[514] | palette jobs buffer |
| uint | *palJobsPtr; | pointer to palettes jobs buffer |
| uint | FIXJOBS[129]; | fix jobs buffer |
| uint | *fixJobsPtr; | pointer to fix jobs buffer |
| uchar | DAT_scratchpad64[64]; | 64 bytes scratchpad |
| uchar | DAT_scratchpad16[16]; | 16 bytes scratchpad |
| | | |

Timer interrupt related variables

| ushort | LSPCmode | requested LSPC mode |
|--------|----------------|---|
| uint | TIbase | timer interrupt timing to first trigger |
| uint | TIreload | timer interrupt reload timing |
| ushort | *TInextTable | pointer to data table to use next frame |
| ushort | Tivalues0[256] | timer interrupt data space 0 |
| ushort | TIvalues1[256] | timer interrupt data space 1 |

General purpose components

MEMBYTE, MEMWORD, MEMDWORD

Direct memory access macros.

Syntax

MEMBYTE(address)
MEMWORD(address)
MEMDWORD(address)

Explanation

Macros that can be used to directly access a memory address or hardware register. Available for byte, word and dword operation.

Ex:

<u>Note:</u> 68000 requires even addresses when operating on word (short - 16bit) and dword (in - 32bit) data. Read/write operation at an odd address for a word/long will crash the CPU.

Return value

VOIMEMBYTE, VOIMEMWORD, VOIMEMDWORD

Direct memory access macros, volatile declaration.

Syntax

volMEMBYTE(address) volMEMWORD(address) volMEMDWORD(address)

Explanation

Macros that can be used to directly access a memory address or hardware register. Available for byte, word and dword operation.

Theses macros are defined with the volatile keyword.

Ex:

```
i=volMEMWORD(0x3c0006);  /* reads LSPC mode register into i */
volMEMWORD(0x300001)=1;  /* kicks watchdog */
```

<u>Note:</u> 68000 requires even addresses when operating on word (short - 16bit) and dword (in - 32bit) data. Read/write operation at an odd address for a word/long will crash the CPU.

Return value

VRAM_SPR_ADDR, VRAM_FIX_ADDR, VRAM_SHRINK_ADDR, VRAM_SHRINK, VRAM_POSY_ADDR, VRAM_POSY, VRAM_POSX_ADDR, VRAM_POSX_

Misc macros for VRAM address calculations and data formating.

Syntax

VRAM_SPR_ADDR1(sprite_number) Sprite tilemap address

VRAM_FIX_ADDR(*X_position*, *Y_position*) Fix address for character at posion x,y **VRAM_SHRINK_ADDR**(*sprite_number*) Sprite shrink coefficient address

VRAM_SHRINK(H_shrink, V_shrink)
VRAM_POSY_ADDR(sprite_number)
VRAM_POSY(Y_position, link, sprite_size)
VRAM_POSX_ADDR(sprite_number)
VRAM_POSX_ADDR(sprite_number)
VRAM_POSX(X_position)
Sprite shrink values
Sprite Y position address
Sprite X position address
Sprite X position value

Explanation

Eases up syntax when handling VRAM values.

Related defines (Y position link value):

SPR_LINK (0x0040) SPR_UNLINK (0x0000)

Ex: Moving sprite #16 to X position 120:

SC234Put(VRAM_POSX_ADDR(16), VRAM_POSX(120));

Return value

fixJobPut

Writes a command into fix jobs buffer. Macro.

Syntax fixJobPut(

Target X position on fix layer Target Y position on fix layer ushort x, ushort y,

ushort mod, VRAM modulo ushort pal, Base palette ushort* data) Pointer to fix data

Explanation

Macro allowing user to put a fix job into fix jobs buffer.

Return value

palJobPut

Writes a command into palette jobs buffer. Macro.

Syntax palJobPut(

Destination palette number (0-255) Number of palettes to write ushort number,

ushort count, Pointer to palette data start ushort* data)

Explanation

Macro allowing user to put a palette job into palette jobs buffer.

Return value

SC1Put

Writes a command into tilemap data draw buffer. Macro.

Syntax

SC1Put(

ushort *addr*, Destination address in VRAM

ushort size,Tile countushort pal,Base palette

ushort* data) Pointer to tilemap data

Explanation

Macro allowing user to put a tilemap command into tilemap data draw buffer (VRAM sprite control block 1).

Maximum valid size is 32 tiles.

Return value

SC234Put

Writes to the sprite control draw buffer. Macro.

Syntax

SC234Put(

ushort addr, Destination address in VRAM

ushort data) Data

Explanation

Macro allowing user writes into the sprite control draw buffer (VRAM sprite control blocks 2 3 & 4).

Whilst designed for sprite control, the usage can be expanded to write any ushort data to any VRAM address.

Return value

clearFixLayer, clearFixLayer2, clearFixLayer3

Clears the fix layer.

Syntax

void clearFixLayer()
void clearFixLayer2()
void clearFixLayer3()

Explanation

Clears the display fix layer.

Clearing is done with tile 0x0ff, make sure it is transparent in your fix data (it will be if using the standard system font).

Totally wipes the fix data, unlike bios FIX_CLEAR function which leaves black bars.

Notes:

- clearFixLayer operates immediately, not on next vblank
- clearFixLayer performs VRAM operations and therefore isn't IRQ safe
- clearFixLayer2 is an IRQ safe version of clearFixLayer
- clearFixLayer3 uses fix command buffer, clear will be performed during next Vblank

Return value

clearSprites

Clears a set of sprites.

Syntax

void clearSprites(

ushort *spr*, First sprite to clear

ushort count) Number of sprites to clear, from starting sprite

Explanation

Clears a block of sprites from spr to spr+count-1.

Sprite clearing is done by unlinking it, setting a 0 size and position it offscreen. Tiledata, shrink values and X position aren't affected.

Return value

disableIRQ

Disables IRQ on the system.

Syntax void disableIRQ()

Explanation

IRQ will no longer be triggered after calling this function.

Disables both IRQ1 and IRQ2.

Return value

enableIRQ

Enables IRQ on the system.

Syntax

void enableIRQ()

Explanation

IRQ will be active after calling this function.

Enables both IRQ1 and IRQ2.

Return value

initGfx

Initialize the library for graphics operations.

Syntax

void initGfx()

Explanation

Resets and sets up library for operation.
Calling this function is required before using the library.

The function notably resets frame counters and unloads timer interrupt function.

Return value

jobMeterColor

Changes current jobmeter color.

Syntax void jobMeterColor(ushort color)

Requested color

Explanation

Macro used to change job meter color to differentiate code segments execution timing.

Return value N/A

jobMeterSetup, jobMeterSetup2

Sets up the job meter.

Syntax

void jobMeterSetup(

bool setDip) Automatic soft dip setting

void jobMeterSetup2(

bool setDip) Automatic soft dip setting

Explanation

Draws the job meter of the fix layer, using fix tile 0x000 and palette 0xf. Make sure that tile is a plain color #1 tile in your fix data for proper display (it will be if using the standard system font). Job meter takes place on the far right column of the fix layer.

For the job meter to be updated during vblank, devmode and soft dip 2-1 must be on.

Call function with *setDip* parameter set to *true* for the function to force bios devmode setting and soft dip 2-1 to on. This basically saves you from enabling them again manually on each boot.

jobMeterSetup2 is an IRQ safe variant of jobMeterSetup.

Note: Forcing bios setting is kind of a hack job, it isn't guaranteed to work on all bios (tested ok on debug bios and uinibios 3.2), try out and use accordingly. Do not use in release code.

Return value

loadTlirq

Loads timer interrupt handler.

Syntax

void loadTlirq(

ushort mode) IRQ mode

Explanation

Loads the required code to process the timer interrupt.

Two modes are available:

- TI_MODE_SINGLE_DATA: One VRAM change per interrupt TI_MODE_DUAL_DATA: Two VRAM changes per interrupt

Return value

SCClose

Readies draw data for display.

Syntax

void SCClose()

Explanation

Closes draw lists and prepare system for next vblank.

SCClose will allow draw lists to be processed upon next VBlank and therefore need to be called before waitVBlank, or the library won't update display and will issue a frameskip.

Return value

setup4P

Initialize 4P input mode.

Syntax

int setup4P()

Explanation

This function will check if a 4P adapter (NEO-FTC1B / NEO-4P) is hooked to the system. It should enable 4 players mode on any bios if hardware is found.

Return value

- 0 adapter was not found
- 1 adapter was found

unloadTlirq

Unloads timer interrupt handler.

Syntax

void unloadTlirq()

Explanation

Unloads the required code to process the timer interrupts.

This actually loads a failsafe handler (acknowledge IRQ then return), shall a timer interrupt occur when unexpected.

<u>Note:</u> make sure you set TinextTable to 0, then wait for a VBlank to occur before using unloadTIirq() to avoid unstable behavior.

Return value

waitVBlank

Waits for next vblank.

Syntax

void waitVBlank()

Explanation

Holds program execution until next vblank is triggered.

Program will resume after the vblank function has been processed.

Return value

String / Text components

About string formats

Text functions can handle two string formats: 8 or 16 bits.

8 bits format: Standard 8 bits character encoding for general purpose use. Ends with a 0x00 character.

16 bits format: 16 bits character encoding aimed for display on fix layer, using VRAM character format.

| 15-12 | 11-8 | 7-0 | |
|----------------|----------------------|--------------------|--|
| Palette number | Character code MSB * | Character code LSB | |

^{*} Character code MSB can be referenced as "bank".

16 bits strings ends with a 0x0000 character.

sprintf2

Formats a text string.

Syntax

ushort sprintf2(

char *dest,char *format,Pointer to destination bufferPointer to format stringExtra arguments

Explanation

Will process the format string and arguments, writing the result into the dest buffer.

This is a streamlined and tweaked alternative to the standard **sprintf** function, allowing faster execution.

Available format tags:

%d: prints an signed integer, decimal format %u: prints an unsigned integer, decimal format

%x: prints an integer, hex format

%c: prints a 8 bit character

%s: prints a string

%0: pads the following argument with zeros

Ex: %08x will print an integer in hex fomat, with a 8 characters size.

Valid sizes are 2-12, encoded as 23456789:; < characters.

%w: prints a 16 bit character (**sprintf3** only)

Return value

Total written characters count, excluding string termination character.

sprintf3

Formats a text string. 16bits fix character format.

Syntax

ushort sprintf3(

ushort palette, Palette number to encode characters with (4 bits)

ushort bank, Fix "bank" (character code MSB (4 bits))

char *dest, Pointer to destination buffer

char *format, Pointer to format string (standard 8 bit characters format)

...) Extra arguments

Explanation

Will process the format string and arguments, writing the result into the dest buffer. Input format string is standard 8bits encoding. Output string is 16bits fix format encoding, using provided palette and bank.

This function is equivalent to **sprintf2**, aside the different output format.

Available format tags: see sprintf2.

Return value

Total written characters count, excluding string termination character.

fixPrint, fixPrint2, fixPrint3, fixPrint4

Displays a character string on the fix layer.

Syntax

void fixPrint(

ushort x,X opsition on the fix layerushort y,Y opsition on the fix layer

ushort pal, Palette # to use

ushort bank, Fix character "bank" (character MSB, 4 bits) **char** *buf) String to print (8bit character format)

void fixPrint2(

ushort x,X opsition on the fix layerushort y,Y opsition on the fix layer

ushort pal. Palette # to use

ushort *bank*, Fix character "bank" (character MSB, 4 bits) **char** *buf) String to print (8bit character format)

void fixPrint3(

ushort x,X opsition on the fix layerushort y,Y opsition on the fix layer

ushort pal, Palette mod (will be added to character palette in string)

char *buf) String to print (16bit character format)

void fixPrint4(

ushort x,X opsition on the fix layerushort y,Y opsition on the fix layer

ushort pal, Palette mod (will be added to character palette in string)

char *buf) String to print (16bit character format)

Explanation

Will print the supplied 8/16bit characters string to the fix layer, using supplied coordinates, palette and/or characters bank.

Functions are not Vblank synced and will print the text immediately during active display. It is therefore advised to use carefuly and/or only for debug messages purpose.

fixPrint2 is an IRQ safe version of fixPrint.

fixPrint4 is an IRQ safe version of fixPrint3.

Return value

fixPrintf, fixPrintf1, fixPrintf2, fixPrintf3

Formats and text string and displays it on fix layer.

```
Syntax
void fixPrintf(
                                         Palette number to encode characters with (4 bits)
        ushort x.
                                         Fix "bank" (character code MSB (4 bits))
        ushort y,
                                         Pointer to destination buffer
        ushort pal,
        ushort bank,
                                         Pointer to format string (standard 8 bit characters format)
        char *format,
                                         Format string pointer
                                         Extra arguments
        ...)
void fixPrintf1(

* Same as fixPrintf *
void fixPrintf2(

* Same as fixPrintf *
void fixPrintf3(
                                         Palette number to encode characters with (4 bits)
        ushort x,
                                         Fix "bank" (character code MSB (4 bits))
        ushort y,
                                         Pointer to destination buffer
        ushort pal.
                                         Pointer to format string (standard 8 bit characters format)
        ushort bank,
        char *buffer.
                                         Buffer pointer for formatted string (16bits format)
        char *format,
                                         Format string pointer (8bit format)
                                         Extra arguments
        ...)
```

Explanation

Will process the format string and arguments, displaying the result on the fix layer. Available format tags: see **sprintf2**.

fixPrintf: standard legacy function from the original neoDev archive. **fixPrintf1**: Similar to **fixPrintf**, but internally using the faster **sprintf2**. **fixPrintf2**: Similar to **fixPrintf1**, but using the IRQ safe **fixPrint2** for display.

fixPrintf3: Uses the supplied buffer to store the resulting formatted 16bits string, and adds display command to the FIXJOBS buffer. Display is Vblank synced.

Return value

Pictures components

picture

Runtime handler for a picture.

Syntax

typedef struct picture {

ushort baseSprite;Base sprite # used for this pictureushort basePalette;Base palette # used for this picture

short posX;Current position, X axisshort posY;Current position, Y axisushort currentFlip;Current flip mode.

pictureInfo* info; Pointer to the pictureInfo struct of this picture

} picture;

Explanation

This is the base structure the library uses to handle picture type elements. Has to be allocated in the ram section of your code.

As operation on this datatype is managed by the library, it is strongly advised to use as read only in your code.

pictureInfo

Structure holding picture information.

Syntax

typedef struct pictureInfo {

ushort *stripSize*; Bytesize of each sprite tilemap (basically tileHeight*4)

ushort tileWidth;Picture width, tiles unitushort tileHeight;Picture height, tiles unitpaletteInfo *palInfo;Pointer to related paletteInfo

ushort *maps[4];
Pointers to tilemaps (standard, flipX, flipY, flipXY)

} pictureInfo;

Explanation

pictureInfo structures are generated by the buildchar tool. Holds basic info about the picture.

Tilemap pointers are always valid. IE if you did not request flipX for that picture in buildChar tool, maps[1] will point to the standard map.

Picture tilemaps bytesize is (tileWidth*tileHeight)*4, or StripSize*tileWidth.

pictureHide

Hide a picture.

Syntax

void pictureHide(picture* p)

Pointer to picture structure to use

Explanation

Removes designated picture element from display.

<u>Note:</u> As hiding is done by altering Y position and sprite size, please be aware that changing Y pos of designated picture will revert it back to visible.

Return value

pictureInit

Initialize a picture structure for use.

Syntax

void pictureInit(

picture* p, Pointer to picture handler to use pictureInfo* pi, Pointer to pictureInfo structure ushort baseSprite, Base sprite # to use ushort basePalette, Base palette # to use short posX, Picture initial X position short posY, Picture initial Y position ushort flip) Picture initial flip mode

Explanation

Initialize and prepare a picture element for use.

Picture will be set up with provided initial position/flip.

Return value

pictureMove

Updates position of a picture entity.

Syntax void pictureMove(

Pointer to picture handler to use X axis offset

picture* p, short shiftX, short shiftY) Y axis offset

Explanation

Change picture screen position.

New position is determined relatively to current position (new pos= current pos + shift).

Return value

pictureSetFlip

Sets flip mode of a picture entity.

Syntax

void pictureSetFlip(

picture* p, ushort flip) Pointer to picture handler to use

Desired flip mode

Explanation

Change picture flip mode.

Flip modes most be specified in your chardata.xml file for the buildchar tool to make them available. Will default to base orientation if requested flip mode isn't available.

Return value

pictureSetPos

Sets position of a picture entity.

Syntax void pictureSetPos(

Pointer to picture handler to use New X position New Y position picture* *ρ*, short *toX*, short toY)

Explanation

Change picture screen position.
Position is set to supplied values.

Return value

pictureShow

Show a picture entity.

Syntax void pictureShow(picture* p

Pointer to picture handler to use

Explanation

Put back a previously hidden picture on display.
Picture will be displayed at latest set position with latest set flip.

Return value

Scrollers components

scroller

Runtime handler for a scroller.

Syntax

typedef struct scroller {

ushort baseSprite;Base sprite # used for this scrollerushort basePalette;Base palette # used for this scroller

ushort scrlPosX;Current scroll index, X axisushort scrlPosY;Current scroll index, Y axis

scrollerInfo* info; Pointer to the scrollerInfo struct of this scroller ushort config[32]; Scroller configuration data - internal use

} scroller;

Explanation

This is the base structure the library uses to handle scroller type elements.

Has to be allocated in the ram section of your code.

As operation on this datatype is managed by the library, it is strongly advised to use as read only in your code.

scrollerInfo

Structure holding scroller information.

Syntax

typedef struct scrollerInfo {

ushort strip *Size;* Bytesize of each sprite tilemap (basically mapHeight*4)

ushort *sprHeight*; Required sprite height to use (max 32)

ushort mapWidth;Scroller width, tiles unitushort mapHeight;Scroller height, tiles unitpaletteInfo *palInfo;Pointer to related paletteInfocolorStreamInfo *csInfo;Pointer to related colorStreamInfo

ushort *strips[0];
Tilemap data (size varies)

} scrollerInfo;

Explanation

scrollerInfo structures are generated by the buildchar tool. Holds basic info about the scroller.

Actual map data size (ushort) is (mapWidth*mapHeight)*2.

Member csInfo wil be 0x00000000 if there is no colorStream related to the scroller.

scrollerInit

Initialize a Scroller entity for use.

Syntax

void scrollerInit(

scroller* *s,* Pointer to **scroller** handler to use **scrollerInfo*** *si,* Pointer to **scrollerInfo** structure

ushort baseSprite,
ushort basePalette,
short posX,Base sprite # to use
Base palette # to use
Scroller initial X position
Scroller initial Y position

Explanation

Initialize and prepare a **scroller** handler for use. **scroller** will be set up with provided initial scroll positions.

Return value

scrollerSetPos

Initialize a **scroller** handler for use.

Syntax

void scrollerInit(

scroller* s, Pointer to **scroller** handler

short toX,
short toY)Scroller X position
Scroller Y position

Explanation

Sets scrolling position of designated **scroller** handler.

Return value

Animated sprites components

aSprite

Runtime handler for an animated sprite.

Syntax

typedef struct aSprite {

ushort baseSprite; Base sprite # used for this animated sprite ushort basePalette; Base palette # used for this animated sprite

short posX;Animated sprite current X positionshort posY;Animated sprite current Y positionushort animID;ID of last requested animation

ushort currentAnim;ID of current animationushort stepNum;Current step number

animStep* anims; Pointer to animations block

animStep* steps; Pointer to steps block of current animation

animStep* currentStep;Pointer to current step datasprFrame* currentFrame;Pointer to current frame datauint counter;Internal frame update counterushort repeats;Number of repeats done

ushort *tileWidth;* Width of current frame, tiles unit

ushort *currentFlip;* Current flip mode

ushort flags; Flags

} aSprite;

Explanation

This is the base structure the library uses to handle animated sprites elements.

Has to be allocated in the ram section of your code.

As operation on this datatype is managed by the library, it is strongly advised to use as read only in your code.

When animation has reached its end (when applicable), counter value will change to 0xffffffff.

Notes:

.currentFlip format is as follows:

| 15-2 | 1 | 0 |
|---------------|---------------|-----------------|
| 0000000000000 | Vertical flip | Horizontal flip |

Related defines:

FLIP_NONE (0)
FLIP_X (1)
FLIP_Y (2)
FLIP_XY (3)
FLIP_BOTH (3)

.flags format is as follows:

| 15-8 | 7 | 6 | 5-2 | 1 | 0 |
|----------|------------|---------------|------|---------|-------|
| 00000000 | No display | Strict coords | 0000 | Flipped | Moved |

Moved / Flipped flags are only relevant when using allocated sprite mode.

Related defines:

| AS_FLAGS_DEFAULT | (0x0000) |
|-----------------------|----------|
| AS_FLAG_MOVED | (0x0001) |
| AS_FLAG_FLIPPED | (0x0002) |
| AS_FLAG_STD_COORDS | (0x0000) |
| AS_FLAG_STRICT_COORDS | (0x0040) |
| AS_FLAG_DISPLAY | (0x0000) |
| AS_FLAG_NODISPLAY | (0x0080) |
| AS_MASK_MOVED | (0xfffe) |
| AS_MASK_FLIPPED | (0xfffd) |
| AS_MASK_MOVED_FLIPPED | (0xfffc) |
| AS_MASK_STRICT_COORDS | (0xffbf) |
| AS_MASK_NODISPLAY | (0xff7f) |

spriteInfo, animStep, sprFrame

Structures holding animated sprites informations.

typedef struct spriteInfo {

ushort frameCount; Total number of frames

ushort maxWidth; Maximum width, tiles unit (width of the largest frame)

paletteInfo *palInfo; Pointer to related paletteInfo animStep **anims;
sprFrame frames[0]; Pointer array to animations

sprFrames array

} spriteInfo;

typedef struct animStep {

sprFrame *frame; Pointer to frame info

short shiftX; Frame X displacement from origin short shiftY: Frame Y displacement from origin u**short** duration; Number of frame to display

} animStep;

typedef struct sprFrame {

ushort tileWidth; Frame width, tiles unit ushort tileHeight; Frame height, tiles unit.

Bytesize of each sprite tilemap (basically tileHeight*4) **ushort** strip*Size*; ushort *maps[4]; Pointers to frame tilemaps (standard, flipX, flipY, flipXY)

} sprFrame;

Explanation

spriteInfo, animStep and sprFrame structures are generated by the buildchar and animator tools. Holds infos about animated sprite frames and animations.

Frame tilemap pointers are always valid. IE if you did not request flipX for that sprite in the buildchar tool, maps[1] will point to the standard map.

Frame tilemaps size (ushort count) are (tileWidth*tileHeight)*2.

aSpriteAnimate

Performs animation updates on an aSprite entity.

Syntax

void aSpriteAnimate(

aSprite* as)

Pointer to aSprite handler to use

Explanation

Updates the aSprite handler animation.

Will apply position/flip/animation changes and queue required commands into draw buffers for update next VBlank.

This function must be called every frame for each animated sprite for proper animation.

Note: this function is for allocated sprites mode, See **spritePoolDrawList** for sprite pool use.

Return value

aSpriteHide

Hides an aSprite entity (macro).

Syntax

void aSpriteHide(

aSprite* as)

Pointer to aSprite handler to use

Explanation

Flag the designated aSprite as no display.

When flagged as no display, animated sprites will no longer be displayed. This allows to keep animating an offscreen/hidden object without having to display it.

<u>Note:</u> If the aSprite is currently used in allocated mode, you must manually clear the sprites used by the current frame => clearSprites(as->baseSprite, as->tileWidth);

Return value

aSpriteInit

Initialize an aSprite entity for use.

Syntax

void aSpriteInit(

aSprite* as,
spriteInfo* si,Pointer to aSprite handler to use
Pointer to spriteInfo structure

ushort baseSprite,Base sprite # to useushort basePalette,Base palette # to useshort posX,aSprite initial X positionshort posY,aSprite initial Y position

ushort *anim*, aSprite initial animation sequence

ushort flipaSprite initial flip modeushort flags)aSprite initial flags

Explanation

Initialize and prepare an aSprite handler for use.

aSprite will be set up with provided initial position, animation, flip mode and flags.

This function will not push frame to display, a call to **aSpriteAnimate** / **spritePoolDrawList** is required after aSpriteInit to push initial frame on display upon next VBlank.

Return value

aSpriteMove

Updates position of an **aSprite** entity.

Syntax

void aSpriteMove(

aSprite* as, Pointer to **aSprite** handler

short shiftX,X axis offsetshort shiftY)Y axis offset

Explanation

Change aSprite handler screen position.

New position is determined relatively to current position (new pos= current pos + shift).

Will not update the display position directly, use **aSpriteAnimate** / **spritePoolDrawList** afterward to apply changes.

 $\underline{\text{Note:}}$ When using sprite pools, you can freely increase or decrease the **aSprite** .posX and .posY fields, without the need of this function.

Return value

aSpriteSetAnim, aSpriteSetAnim2

Sets animation for an aSprite entity.

Syntax

void aSpriteSetAnim(

aSprite* as, Pointer to **aSprite** handler

ushort anim) Animation ID

void aSpriteSetAnim2(

aSprite* as, Pointer to **aSprite** handler

ushort anim) Animation ID

Explanation

Change current animation.

Animation IDs are defines issued by the animator tool, see documentation for syntax.

Will not push frame to display, use **aSpriteAnimate** / **spritePoolDrawList** afterward to apply changes. If requesting change to the animation sequence ID that is already running, nothing will be done.

About animation links:

When using linked animations (ie A > B > C (loop)) system will remember "A" as last requested animation ID.

This means if said animated sprite ran long enough to reach animation "C", a request for animation ID "A" might be discarded as this is the last requence requested and running.

aSpriteSetAnim will discard animation requests of the same ID.

aSpriteSetAnim2 will set animation regardless of current state. If the same animation is already running, it will be rewinded/reset.

Return value

aSpriteSetStep, aSpriteSetStep2

Sets step number for an aSprite entity.

Syntax

void aSpriteSetStep(

aSprite* as, Pointer to **aSprite** handler

ushort step) Step number

void aSpriteSetStep2(

aSprite* as, Pointer to **aSprite** handler

ushort step) Step number

Explanation

Moves current animation of the provided **aSprite** handler to selected step number.

aSpriteSetStep will discard request if current step is the same as requested.

aSpriteSetStep2 will set step regardless of current state. If the same step is already displayed, step timing will be reset.

Return value

aSpriteSetAnimStep, aSpriteSetAnimStep2

Sets animation and step number for an aSprite entity.

Syntax

void aSpriteSetAnimStep(

aSprite* as, Pointer to **aSprite** handler

ushort anim,Animation IDushort step)Step number

void aSpriteSetAnimStep2(

aSprite* as, Pointer to **aSprite** handler

ushort anim,Animation IDushort step)Step number

Explanation

Changes current animation of privided aSprite handler, running from the choosen step number.

Animating rules applied are the same as aSpriteSetAnim.

aSpriteSetAnimStep will discard request if current animation and step is the same as requested. **aSpriteSetAnimStep2** will set animation and step regardless of current state. Step timing will be reset if parameters are same as current state.

Return value

aSpriteSetFlip

Sets flip mode of an aSprite entity.

Syntax

void aSpriteSetFlip(

aSprite* *as,* Pointer to **aSprite** handler **ushort** *flip*) Desired flip mode

ExplanationChange **aSprite** handler flip mode.

Flip modes most be specified in your chardata.xml file for the buildchar tool to make them available. Will default to base orientation if requested flip mode isn't available.

<u>Note:</u> When using sprite pools, you can freely set requested flip mode directly into the **aSprite**.currentFlip field, without the need of this function.

Return value

aSpriteSetPos

Sets position of an **aSprite** entity.

Syntax

void aSpriteSetPos(

aSprite* as, Pointer to aSprite handler

short newX,New X positionshort newY)New Y position

Explanation

Change aSprite handler screen position.

Will not update the display position directly, use **aSpriteAnimate** / **spritePoolDrawList** afterward to apply changes.

<u>Note:</u> When using sprite pools, you can freely set coordinates directly into the **aSprite** .posX and .posY fields, without the need of this function.

Return value

aSpriteShow

Reverts an hidden aSprite entity to visible. (macro).

Syntax void aSpriteShow(aSprite* as)

Pointer to aSprite handler

Explanation

Removes the no display flag from the designated **aSprite**.

Returns the aSprite to its normal state, allowing it to be displayed again.

Has no effect if aSprite handler is already flaged as visible.

Return value

Sprite Pools components

spritePool

Runtime handler for a sprite pool.

Syntax

typedef struct spritePool {

ushort poolStart;Fist sprite # to be used for this sprite poolushort poolEnd;Last sprite # to be used for this sprite pool

ushort *poolSize;* Sprite pool size

ushort *way;* Current draw direction

ushort currentUp;Current spr index - internal useushort currentDown;Current spr index - internal use

} spritePool;

Explanation

This is the base structure the library uses to handle sprite pools elements.

Has to be allocated in the ram section of your code.

As operation on this datatype is managed by the library, it is advised to manipulate only using provided functions.

Related defines:

WAY_UP (0) WAY_DOWN (1)

spritePoolClose

Finalize sprite pool operations for display.

Syntax

ushort spritePoolClose(spritePool *sp)

Pointer to **spritePool** handler

Explanation

Prepares a spritePool for next VBlank.

Needs to be called before each VBlank, will switch pool direction and queue the necessary sprite clears for correct display.

Note: Sprite pool passed to this function is not to be used before next Vblank has occurred.

Return value

Will return 1 when draw operations exceeded total pool size, 0 otherwise.

spritePoolDrawList, spritePoolDrawList2

Draws the supplied animated sprites list into sprite pool.

Syntax

void spritePoolDrawList(

spritePool *sp Pointer to spritePool handler

void *list) Pointer to draw list

void spritePoolDrawList2(

spritePool *sp Pointer to spritePool handler

void **list*) Pointer to draw list

Explanation

Utilize the supplied spritePool to render the aSprite entities in the supplied list.

This function takes care of updating the aSprite animation state, then display the updated entity.

Notes: User must supply a list pointer according to the current direction of the sprite pool :

- o WAY_UP: list must point to the first item, list will be read upward until null is found
- WAY_DOWN: list must point to the <u>last+1</u> element, list will be read downward until null is found

SpritePoolDrawList isn't IRQ safe.

SpritePoolDrawList2 is an IRQ safe variant of spritePoolDrawList.

Return value

spritePoolInit

Initialize the supplied sprite pool handler.

Syntax

void spritePoolInit(

spritePool *sp,Pointer to spritePool handlerushort baseSprite,Startig sprite of sprite poolushort poolSize,Sprite pool sizebool clearSprites)Sprites clear flag

Explanation

Sets up the supplied **spritePool** handler for use.

If *clearSprites* is set to ture, **spritePoolInit** will buffer a sprite clear of sprites *baseSprite* to *baseSprite+poolSize-1*.

Return value

Color steam components

colorStream

Runtime handler for a color stream.

Syntax

typedef struct colorStream {

ushort basePalette;Base palette # used for this color streamushort position;Holds current position in stream – internal use

colorStreamInfo *info; Pointer to related colorStreamInfo

colorStreamJob *fwJob; Pointer to next job, forward way – internal use Pointer to next job, backward way – internal use

} colorStream;

Explanation

This is the base structure the library uses to handle color streams elements. Has to be allocated in the ram section of your code.

As operation on this datatype is managed by the library, it is strongly advised to use as read only in your code.

colorStreamInfo, colorStreamJob

Structures holding color stream informations and data.

Syntax

typedef struct colorStreamInfo {

ushort palSlots; Number of palettes required to operate the **colorStream**

void *startConfig;Pointer to start configuration datavoid *endConfig;Pointer to end configuration datavoid *fwData;Pointer to forward stream datavoid *fwDataEnd;Pointer to end of forward stream datavoid *bwData;Pointer to backward stream datavoid *bwDataEnd;Pointer to end of backward stream data

} colorStreamInfo;

typedef struct colorStreamJob {

ushort coord;Stream update coordinatevoid *data;Pointer to update data

} colorStreamJob;

Explanation

colorStreamInfo and **colorStreamJob** structures are generated by the buildchar tool. Holds informations about color streams.

Configurations and jobs format are as follows:

.word 0x0012 ; palette slot #

.long 0x00123456 ; pointer to palette data

. . .

.word 0xffff ; end marker

colorStreamInit

Initialize the supplied color stream handler.

Syntax

void colorStreamInit(

colorStream *cs, Pointer to colorStream handler

colorStreamInfo *csi, Pointer to related colorStreamInfo structure

ushort basePalette,Base palette # to useushort config)Start configuration

Explanation

Sets up the supplied colorStream handler for use.

Will buffer the required palette jobs to set up the requested start config.

Related defines:

COLORSTREAM_STARTCONFIG (0) COLORSTREAM_ENDCONFIG (1)

Return value

colorStreamSetPos

Updates the stream position of supplied color stream handler.

Syntax

void colorStreamSetPos(

colorStream *cs, Pointer to colorStream handler

ushort *pos*) New stream position

Explanation

Advances or rewinds the supplied **colorStream** to the requested position.

colorStreamSetPos will buffer the required palette commands to update the color stream up to the designated position.

Return value